56 - Kommandos später ausführen mit at & batch

at Runs a command only once at a predetermined time.

batch

command is only a script and does the same as <u>at</u> except that it executes commands when system load levels permit; in other words, when the load average drops below 0.8

Syntax:

at [options] time
batch [options] time

How to launch an AT job:

- 1. Type at and any options and time of execution
- 2. Enter the command(s) you want to run (press Enter after each command)

 Note: The commands MUST contain the full path of the command.
- Press Ctrl-D to save the job(s).

· at options:

- -b Run command only when the system load is low
- -d jobNr Delete an at job from queue (same as atrm)
- -f filename

Read job from a specified file

- -1 List all jobs for that user. If user is root, shows all jobs.
- -m Mails user when job completes.
- -q queueName

Send the jobs to a specific queue.

Queue names are single letters: **a** to **z** and **A** to **Z a** is the default and set highest AT priority (nice=2).

b is the default for batch command queues. The higher the letter the higher the <u>nice</u> value

(less priority). nice of: a=2 b=4 c =6 d=8 etc.

Time formats

now
Well....NOW!
17:00
At 17:00 hours
In 3 hours from now
In 2 minutes from now
Hand the second of the seco

allowed formats:

MMDDYY, MM/DD/YY, DD.MM.YY

now, noon, teatime (4pm), midnight, today, tomorrow

• 4PM At 4 pm today if not too late

otherwise tomorrow at 4PM

• 16:00 + 3 days At 16:00 hous in 3 days

• mon Next Monday same time. Days are:

non, tue, wed, thu, fri, sat, sun

• 18:25 31 march 2001 On march 31 2001 at 18:25

• atq Show the AT jobs queue of user. Incl jobsNumbers If user is root, shows all jobs. Same as at -1

• atrm jobNr [jobNr] ... Deletes an AT job from the jobs queue AT Command on one line(useful in scripts):

```
echo "command1;comman2;..." | at time eg.
```

xhost + localhost
echo "xmessage -display :0 'It works'" | at +1 minutes
watch -n1 atq

Files involved:

/var/spool/atjobs Where the jobs are stored.

at Produces jobs starting with a if queue is not given (-q). These jobs is a snapshot of environment variables plus the

commands given.

/var/spool/atspool Same as /var/spool/atjobs

/proc/loadavg Average system load value that gives a one line display of

the following information: The current time, how long the system has been running, how many users are currently logged on, and the system load averages for the past 1, 5,

and 15 minutes.

/var/run/utmp Uptime of the processes list in binary format. Used to

determine the system load averages.

/etc/at.allow List of users that are allowed to use the commands batch

and at.

If present: /etc/at.deny is ignored (If at all present) and

all the users that are not listed here are NOT allowed.

/etc/at.deny List of users that are NOT allowed to use the command

batch and at.

If present and /etc/at.allow is NOT present, then all

users are allowed except the ones listed here.

Alternatives to **at** and **Batch**: consider another batch system like **nqs**.