

69 - SQUID - Proxy Server

SQUID2 - Proxy Server Users Manual

Table of Contents (see SQUID_Proxy_Server_Users_Manual.sdw for the details)

What is Squid?	3
Concepts behind internet caching	3
What Systems does Squid run on?	3
Precompiled versions of squid	4
Before you start compiling	4
Getting the Source	4
Compiling Squid	4
Directory structure	5
Basic configuration	5
Basic.conf.txt.....	6
Running squid	6
Basic client software configuration	7
Netscape 3	7
Microsoft's Internet Explorer.....	7
Netmanage Internet Chameleon Websurfer	7
Generic Unix configuration	7
Advanced client configuration	8
Netscape 3	8
Internet Explorer	8
The Java Script	9
Access controls	10
Basics	10
More advanced options	10
More Configuration Details.....	12
Cache accelerator mode	12
Why run an accelerator?	12
Configuring Squid as an Accelerator	12
Cache Hierarchies.....	13
Concepts	13
Parent's vs Siblings	14
Integration with other software	15
Getting other software to talk to your Squid cache as a parent	15
Log analysis and stats.....	16
Introduction	16
Tools	17
Analysis	17
Additional Software and misc.....	18
Preloading pages	18
Bottlenecks and performance issues.....	19
Bottlenecks and performance tuning.....	19
Specific Bottlenecks.	19
Optimisation/Optimization.....	22
Malloc problems and memory usage	22
System software you can use to analyze squid	22

More Information.....23

- Squid's home page and related info23
- Mailing Lists:.....23
- Be friendly.....23
- Credits and wonderful people who contributed to this document23
- Inverse thanks..... 23

SQUID2 - Proxy Server (mics. docs).....23

- Readme.....24
- Debug-Sections.....24
- squid2-Changes.....26
- HTTP-Codes.txt.....27
- INSTALL.....28

Notes:

- When Squid starts:
 - Squid reads the `/etc/host.conf` to find the sequence of name resolve
 - If `order hosts bind` then it takes a snapshot of the `/etc/hosts`
 - it then checks if the directive `dns_nammeservers` exist in `/etc/squid.conf`
 - if yes then it uses these DNS Servers for name resolution
 - otherwise it uses the `/etc/resolv.conf` if it exists.
 - It then starts some DNS-Serving-Daemons called `[dnsserver]`

● How can I purge an object from my cache?

Squid does not allow you to purge objects unless it is configured with access controls in `squid.conf`. First you must add something like

```
acl PURGE method purge
acl localhost src 127.0.0.1
http_access allow purge localhost
http_access deny purge
```

The above only allows purge requests which come from the local host and denies all other purge requests.

To purge an object, you can use the client program:

```
client -m PURGE http://www.miscreant.com/
```

If the purge was successful, you will see a ``200 OK" response:

```
HTTP/1.0 200 OK
Date: Thu, 17 Jul 1997 16:03:32 GMT
Server: Squid/1.1.14
```

If the object was not found in the cache, you will see a ``404 Not Found" response:

```
HTTP/1.0 404 Not Found
Date: Thu, 17 Jul 1997 16:03:22 GMT
Server: Squid/1.1.14
```

● **How can I assign different bandwidth to different squid clients?**

Squid has the possibility to limit the `http/https/ftp` bandwidth via 'delay pools'.

The procedure is as follows:

- Assignment of acl aliases to groups of hosts.
- Create 'delay pools' and assign a class type to each pool.
- Assign bandwidth parameters to each pool
- Assign each acl group to a 'delay pool'.

Example No1:

We want to assign two bandwidth:

- 512kbit/s(64000 Bytes/s) for the office hosts
- 128kbit/s(16000 Bytes/s) for hosts of rest of the company

Configuration in `/etc/squid.conf`:

```
acl office_hosts src 192.168.71.10 192.168.71.44 192.168.71.242
acl intranet src 192.168.71.0/255.255.255.0
```

Create 2 delay pools

```
delay_pools 2
```

Assign a class type to each delay pool

Class 1 has class type 2

```
delay_class 1 2
```

Class 2 has class type 2

```
delay_class 2 2
```

Assign bandwidth to each pool

Pool 1 get no overall limit(-1/-1) but each host is limited to max 64KBytes/sec.

```
delay_parameters 1 -1/-1 64000/64000
```

Pool 2 get no overall limit(-1/-1) but each host is limited to max 16KBytes/sec.

```
delay_parameters 2 -1/-1 16000/16000
```

Assign each pool to the hosts groups

```
delay_access 1 allow office_hosts
```

```
delay_access 2 allow intranet
```

Example No2:

We want to assign a single bandwidth limit:

- 8KBytes/s to a all hosts in 2 subnets (192.168.70.0/24 and 192.168.71.0/24)
- No bandwidth limit for some special hosts in those 2 subnets.

Configuration in `/etc/squid.conf`:

Assign acl to host groups

```
acl intranets src 192.168.70.0/255.255.254.0
```

```
acl special_hosts src 192.168.71.10 192.168.71.42 192.168.71.44\
    192.168.71.130 192.168.70.10 192.168.70.130 192.168.71.201
```

Create 1 delay pool

```
delay_pools 1
```

Assign the class 2 to pool 1

```
delay_class 1 2
```

Assign bandwidth parameters to pool 1

Pool 1 gets no overall limit(-1/-1) but each host is limited to 8KBytes/s

```
delay_parameters 1 -1/-1 8000/8000
```

Assign pool 1 to hosts group(acls)

Notice that `special_hosts` are simply denied access to the pool1 therefore getting no bandwidth limit. To achieve this, the deny rule must be declared first.

```
delay_access 1 deny special_hosts
delay_access 1 allow intranets
```

This above examples are some of the most useful configurations I've found so far. The following squid configuration file of SuSE 9.x explains in more details the different possibilities.

```
# DELAY POOL PARAMETERS (all require DELAY_POOLS compilation option)
#-----

# TAG: delay_pools
#   This represents the number of delay pools to be used.  For example,
#   if you have one class 2 delay pool and one class 3 delays pool, you
#   have a total of 2 delay pools.
#
#   To enable this option, you must use --enable-delay-pools with the
#   configure script.
#
#Default:
# delay_pools 0

# TAG: delay_class
#   This defines the class of each delay pool.  There must be exactly one
#   delay_class line for each delay pool.  For example, to define two
#   delay pools, one of class 2 and one of class 3, the settings above
#   and here would be:
#
#Example:
#+-----+

# delay_pools 2      # 2 delay pools
# delay_class 1 2    # pool 1 is a class 2 pool
# delay_class 2 3    # pool 2 is a class 3 pool
#
#   The delay pool classes are:
#
#   class 1          Everything is limited by a single aggregate bucket.
#
#   class 2          Everything is limited by a single aggregate bucket
#                   as well as an "individual" bucket chosen
#                   from bits 25 through 32 of the IP address.
#                   (Individual hosts in a class C network)
#
#   class 3          Everything is limited by a single aggregate bucket
#                   as well as a "network" bucket chosen
#                   from bits 17 through 24 of the IP address
#                   (Overall limit for each Class C subnet)
#                   and a "individual" bucket chosen
#                   from bits 17 through 32 of the IP address.
#                   (Individual limit for each host in a class C network)
#
#   NOTE: If an IP address is a.b.c.d
#         -> bits 25 through 32 are "d"
#         -> bits 17 through 24 are "c"
#         -> bits 17 through 32 are "c * 256 + d"
#
#Default:
# none
```

```
# TAG: delay_access
# This is used to determine which delay pool a request falls into.
# The first matched delay pool is always used, i.e., if a request falls
# into delay pool number one, no more delay are checked, otherwise the
# rest are checked in order of their delay pool number until they have
# all been checked. For example, if you want some_big_clients in delay
# pool 1 and lotsa_little_clients in delay pool 2:
#
#Example:
# delay_access 1 allow some_big_clients
# delay_access 1 deny all
# delay_access 2 allow lotsa_little_clients
# delay_access 2 deny all
#
#Default:
# none
# TAG: delay_parameters
# This defines the parameters for a delay pool. Each delay pool has
# a number of "buckets" associated with it, as explained in the
# description of delay_class. For a class 1 delay pool, the syntax is:
#
#delay_parameters pool aggregate
#
# For a class 2 delay pool:
#
#delay_parameters pool aggregate individual
#
# For a class 3 delay pool:
#
#delay_parameters pool aggregate network individual
#
# The variables here are:
#
# pool          a pool number.
#                ie, a number between 1 and the number specified in
#                delay_pools as used in delay_class lines.
#
# aggregate     the "delay parameters" for the aggregate bucket
#                (Overall bandwidth for the sum all hosts of the pool)
#                (class 1, 2, 3).
#
# network       the "delay parameters" for the network buckets
#                (class 3 only).
#
# individual    the "delay parameters" for the individual buckets
#                (Bandwidth for each individual host)
#                (class 2 and 3 only).
#
# A pair of delay parameters is written restore/maximum, where
# - restore is the number of bytes (not bits - modem and
#   network speeds are usually quoted in bits)
#   per second placed into the bucket,
# - maximum is the maximum number of bytes which can be in
#   the bucket at any time.
#
# For example, if delay pool number 1 is a class 2 delay pool as in the
# above example, and is being used to strictly limit each host to 64kbps
# (plus overheads), with no overall limit, the line is:
#
#delay_parameters 1 -1/-1 8000/8000
#
# Note that the figure -1 is used to represent "unlimited".
```

```
#
#   And, if delay pool number 2 is a class 3 delay pool as in the above
#   example, and you want to limit it to a total of 256kbps (strict limit)
#   with each 8-bit network permitted 64kbps (strict limit) and each
#   individual host permitted 4800bps with a bucket maximum size of 64kb
#   to permit a decent web page to be downloaded at a decent speed
#   (if the network is not being limited due to overuse) but slow down
#   large downloads more significantly:
#
#delay_parameters 2 32000/32000 8000/8000 600/64000
#
#   There must be one delay_parameters line for each delay pool.
#
#Default:
# none

# TAG: delay_initial_bucket_level (percent, 0-100)
#   The initial bucket percentage is used to determine how much is put
#   in each bucket when squid starts, is reconfigured, or first notices
#   a host accessing it (in class 2 and class 3, individual hosts and
#   networks only have buckets associated with them once they have been
#   "seen" by squid).
#Default:
# delay_initial_bucket_level 50
```